

Vista Instructions

- 1 Set up 2 user accounts with administrator privileges
When setting up these accounts, remember to set a password.
for example:
account name: admin password: <whatever you want>
account name: public password: public
These instructions will assume that you will be using these two user accounts.
- 2 Log into the '**public**' account
- 3 Access the '**User Account Control**' in the '**User Accounts**' and turn off/disable
This will ask you to reboot your computer, do so and then log back in as '**public**'
- 4 After the reboot
Finish installing all the desired software that you would like the customers to use.
Install the SmartTimer Client Software and run it
Configure any firewall software (i.e. windows firewall) to allow the smarttimer client (client.exe) and other desired software to communicate to the internet.
- 5 Apply Smarttimer Advanced Security and automatic log onto windows
To apply these settings
Enter in the Smarttimer override code to access the smarttimer control panel.

To apply **advanced security** click on the **Install** button on the left hand side of the control panel.

To apply automatic login click on the 'Advanced Security' button then click on the button titled 'Other Features'

Fill in the username '**public**'
Fill in the password '**public**' (*do not include the quotation marks*)
Click the '**Automatically Log into Windows**' option (*so it shows the tick mark*)
Click the check option '**Click this to confirm all saved settings**' to also show the tick.
6. Reboot the PC
It should now automatically log in under the '**public**' account and start the SmartTimer client software with all security settings applied.
Test the system by using a normal PIN to ensure security is activated etc.
Log out of smarttimer (back to the '**Enter your PIN**' screen).
7. Press CTRL-ALT-DEL and select '**switch user**'.
Login with the '**Admin**' Account that you have created
8. Go to '**user accounts**' and change the '**public**' account's account type from **administrator** to **standard user**.
Turn '**User Account Control**' back on.
9. Reboot PC, it is now ready to be used by the general public after purchasing PIN.

Windows 7 Instructions

- 1 Set up 2 user accounts with administrator privileges
When setting up these accounts, remember to set a password.
for example:

account name: admin password: <whatever you want>
account name: public password: public

These instructions will assume that you will be using these two user accounts.

- 2 Log into the '**public**' account

- 3 Disable User Account Control

1. Go to Start Menu -> Control Panel -> System and [Security](#) -> Action Center.
2. Click on User Account Control settings link
3. Slide the slider bar to the lowest value (towards Never Notify), with description showing Never notify me

Choose when to be notified about changes to your computer

User Account Control helps prevent potentially harmful programs from making changes to your computer.
[Tell me more about User Account Control settings](#)



4. Click OK to make the change effective
5. Reboot the computer

- 4 After the reboot

Finish installing all the desired software that you would like the customers to use.

Install the SmartTimer Client Software and run it

Configure any firewall software (i.e. windows firewall) to allow the smarttimer client (client.exe) and other desired software to communicate to the internet.

- 5 Apply Smarttimer Advanced Security and automatic log onto windows

To apply these settings

Enter in the Smarttimer override code to access the smarttimer control panel.

To apply **advanced security** click on the **Install** button on the left hand side of the control panel.

To apply automatic login click on the 'Advanced Security' button then click on the button titled 'Other Features'

Fill in the username '**public**'

Fill in the password '**public**' (do not include the quotation marks)

Click the '**Automatically Log into Windows**' option (*so it shows the tick mark*)
Click the check option '**Click this to confirm all saved settings**' to also show the tick.

6. Reboot the PC
It should now automatically log in under the '**public**' account and start the SmartTimer client software with all security settings applied.
Test the system by using a normal PIN to ensure security is activated etc.
Log out of smarttimer (back to the '**Enter your PIN**' screen).
7. Press CTRL-ALT-DEL and select '**switch user**'.
Login with the '**Admin**' Account that you have created
8. Reenable User Account Control by following the instructions in Step 3, but raising the slider towards always notify.
9. Reboot PC, it is now ready to be used by the general public after purchasing PIN.